


Bluetooth Install





▶ Bluetooth Adapter Installation


- ▶ Insert the driver software CD into your computer's optical drive.
 - ▶ Follow the on-screen instructions.
 - ▶ When the "Bluetooth Device Not Found" or "No Bluetooth device was detected" window appears. Insert the USB Bluetooth adapter in the USB port.
 - ▶ Note: Do not connect the Adapter to your computer ~until the software drivers are installed.
 - ▶ Follow the on-screen instructions then click Finish to complete the installation.
 - ▶ If your computer does not have an optical drive, you can download the latest driver from WWW.targus.com
- 



▶ **Basic Operations**

- ▶ To start Bluetooth in the Windows system tray, right-click the Bluetooth icon and select Start the Bluetooth Device / Turn Adapter On. The Bluetooth icon is blue in color with a white insert when the Bluetooth software is running.
- ▶ To stop Bluetooth in the Windows system tray, right-click the Bluetooth icon and select Stop the Bluetooth Device / Turn Adapter Off. The Bluetooth icon is blue in color with a red insert when Bluetooth is stopped.

▶ **Verifying the Adapter is installed**


- ▶ After installing the adapter software (for Vista / 7 / 8):
 - ▶ Click Start/Control Panel/Hardware/Device Manager.
 - ▶ Check under 'Bluetooth Radios' that a 'Broadcom BCM 20702 Bluetooth 4.0 USB device" is installed.
- 



▶ Configuring Bluetooth Devices

- ▶ The Bluetooth tray resides in the Windows system tray, which is normally located in the lower-right corner of the screen. The Bluetooth tray provides fast access to most Bluetooth Operations.

▶ **From the Bluetooth tray you can (Windows 8/7 / Vista):**

- ▶ Add a Bluetooth device: right-click the Bluetooth icon and then select Add a Device.
 - ▶ Show a Bluetooth device: right-click the Bluetooth icon and then select Show Bluetooth Device.
 - ▶ Access the Bluetooth Configuration Panel: right-click the Bluetooth icon, and then select Open Settings.
- 

Install Bluetooth Software for Win 7 / Vista

Install Bluetooth Software for Win 8

Quit

WIDCOMM Bluetooth Software



Bluetooth software installation folder:

C:\Program Files\WIDCOMM\Bluetooth Software\

Select another folder...


→ Agree and Install Bluetooth Software

You have read and agreed to the terms of the license agreement. Click to start the installation process.

→ Do not install

You do not want to install this software and would like to exit this program.

By installing this software application, you agree you have read and accepted the [Bluetooth End User License Agreement](#)



WIDCOMM Bluetooth Software

Remote Keyboard and Mouse



Control other devices with your local keyboard and mouse.

The diagram shows a laptop on the left connected by blue arrows to a keyboard and mouse in the center. From these peripherals, three blue arrows point to three different mobile devices on the right: a smartphone, a tablet, and a laptop. A large, faint watermark of a stylized 'W' with a play button is visible in the background.

WIDCOMM Bluetooth Software

Hands-Free Audio



Use Bluetooth hands-free devices to do calls over Skype™ or other VoIP applications.

The diagram shows a laptop on the left connected by a blue line to a central 'skype' logo. From the logo, a blue line connects to a silver hands-free headset on the right. A large, faint watermark of a stylized 'W' with a play button is visible in the background.

WIDCOMM Bluetooth Software

Stereo Speakers




Play music from your phone directly to computer speakers.

The diagram illustrates a laptop on the left and a smartphone on the right. A blue line connects them, passing through a large, stylized Bluetooth symbol in the center. The symbol is light blue and semi-transparent. The background is a light gray gradient. The text 'Play music from your phone directly to computer speakers.' is at the bottom. A green progress bar is partially visible at the bottom left.


WIDCOMM Bluetooth Software

Mouse And Keyboard



Use a Bluetooth mouse or keyboard.

The diagram illustrates a laptop on the left and a keyboard and mouse on the right. A blue line connects them, passing through a large, stylized Bluetooth symbol in the center. The symbol is light blue and semi-transparent. The background is a light gray gradient. The text 'Use a Bluetooth mouse or keyboard.' is at the bottom. A green progress bar is partially visible at the bottom left.



WIDCOMM Bluetooth Software

Video




Use your phone as a WebCam for your computer.

WIDCOMM Bluetooth Software

WIDCOMM Bluetooth Software

Personal Information



Backup, restore or synchronize contacts, calendar, email, notes.



WIDCOMM Bluetooth Software

← PC and devices

- Lock screen
- Display
- Bluetooth**
- Devices
- Mouse and touchpad
- Typing
- Corners and edges
- Power and sleep
- AutoPlay
- Disk space
- PC info

Manage Bluetooth devices

Your PC is searching for and can be discovered by Bluetooth devices.



-  SGH-A997M
Paired
-  RCA RTS7110B
Ready to pair

← PC and devices

- Lock screen
- Display
- Bluetooth**
- Devices
- Mouse and touchpad
- Typing
- Corners and edges
- Power and sleep
- AutoPlay
- Disk space
- PC info

Manage Bluetooth devices


Your PC is searching for and can be discovered by Bluetooth devices.

-  SGH-A997M
Paired
-  RCA RTS7110B
Ready to pair

SGH-A997M

In Bluetooth Device Control, you can connect to and disconnect from device services and configure device settings.

Bluetooth Device Control



MSALTER-PC — Bluetooth — SGH-A997M (Disconnected)

Phone Operations

File Transfer

Browse the files on the (SGH-A997M) phone
Send files to the (SGH-A997M) phone

Music and Audio

Play audio stored on the (SGH-A997M) phone through my computer

Remote Keyboard and Mouse

Control other devices using keyboard and mouse of your computer


Settings

File Exchange settings

RCA RTS7110B

In Bluetooth Device Control, you can connect to and disconnect from device services and configure device settings.

Bluetooth Device Control



MSALTER-PC — Bluetooth — RCA RTS7110B (Connected)

Headset Operations

Music and Audio

Disconnect from the Bluetooth (RCA RTS7110B) headset

Settings

Headset type

